



Barnes & Noble Nook



1. Find the items you wish to borrow (downloads.live-brary.com) and add them to your ‘cart’ (If you are downloading a single item, you must still add the item to your cart to download it)
 - a. You are allowed to have a maximum of 5 items borrowed on your account at any time
 - b. Be sure that the item you want to borrow is compatible with your portable device
 - i. Audiobooks cannot play on the Nook
 - c. If there are no available copies of the item, you can click ‘Add to Wait List’ for it and you will be notified via email when a digital copy is available for you to download
2. Check the items out in your ‘cart’ by selecting your home library from the dropdown list and entering your library card barcode or username
 - a. Some items allow you to choose a lending period for them so you can choose to have the item expire sooner, which would enable you to borrow another item, or expire a little later to give you more time to finish reading it
3. Before you can download items onto your computer, you will need to download the software that helps you download and use eBooks. This software is free and completely safe to load onto your computer. All software is available via the “Required Software” link on our Downloads site

Adobe ePub and pdf eBooks

REQUIRES: Adobe Digital Editions (ADE) software

- Adobe ePub and pdf eBooks will download into the Adobe Digital Editions (ADE) software
- You must activate your copy of Adobe Digital Editions before you can begin using the software
 - Activating Adobe Digital Editions using an Adobe ID allows you to do more with Adobe eBooks, such as downloading them on multiple computers and transferring them to supported portable devices
 - Adobe IDs are free at Adobe’s website
 - It simply requires a name, email address, password and some basic location information
 - Your email address becomes your Adobe ID
- Activating Adobe Digital Editions anonymously allows you to ONLY use the downloaded eBooks on a single computer
 - You will NOT be able to use the eBooks on any portable device

4. Download the items onto your computer. If you have more than one item in your cart, you must download each one individually
 - a. For Adobe eBooks, click on ‘Download’ then click on ‘Open’
 - i. Adobe Digital Editions will open automatically and the title will download directly into the software

5. Upload the items from your computer to your portable device:

Adobe ePub and pdf eBooks

REQUIRES: Adobe Digital Editions (ADE) software

1. Turn on your Nook and plug it into your computer
2. Open your Adobe Digital Editions (ADE) software
3. Adobe Digital Editions launches and detects your Nook. The 'Device Setup Assistant' dialog box is displayed
4. Click 'Authorize Device'
5. Both your computer and your Nook must be activated to use Adobe eBooks
 - a. You must activate your Nook with the same Adobe ID as your computer to transfer Adobe eBooks to it. Your Adobe ID is the email address and password you entered when activating the software on your computer
6. Select the 'Library View' icon (in the upper left corner). Your Nook should appear in the Bookshelves list
7. Drag and drop the Adobe eBook you wish to transfer to the Nook icon in the left pane of Adobe Digital Editions

6. Your eBooks will be in the My Documents folder on your Nook. Click “Check for new content”
7. Downloaded items automatically expire after the loan period is up, you do NOT have to return them
 - a. eBooks that have been downloaded into Adobe Digital Editions software may be returned early
 - i. Click on the arrow above the top left corner of your book and select ‘Return Borrowed Item’
 1. This will free up one of your 5 maximum checkouts for another item
 - b. You are responsible for deleting expired items in Mobipocket Reader, Adobe Digital Editions, and any copies uploaded to a portable device
8. If you have any trouble, feel free to use the Help feature on the web site or call your local library staff for assistance

TROUBLESHOOTING

- If you have a problem dragging and dropping the eBooks in ADE, you can manually copy the book from the “Digital Editions” directory in your computer’s “Documents” folder into the “My Documents” folder on your Nook
- If the Nook does not show in ADE, some Nook readers come with an Adobe ADE type directory preinstalled. It MUST be deleted from the Nook before ADE will recognize the Nook. Close ADE. Find and delete the .adobe-digital-editions file on the Nook. Open ADE. The Nook should now show in the Bookshelves list on ADE
- If you can’t open your downloaded book, try going to your downloads Directory on your Nook and finding the file. It will end in .ascm - just double-click it to open it



SACHEM PUBLIC LIBRARY · 150 HOLBROOK ROAD · HOLBROOK, NY 11741 (631) 588-5024